

Python

Install Python 3.6 Software Collection

```
$ sudo yum install rh-python36
$ scl enable rh-python36 bash
```

PyPi Mirroring - Devpi Server

```
$ mkdir /srv/www/devpi/ && mkdir /srv/www/devpi/data/ && cd /srv/www/devpi
$ virtualenv env
$ ./env/bin/pip install -q -U devpi-server

$ devpi-server --port 4040 --serverdir ./data/ --gen-config

$ cp gen-config/devpi.service /etc/systemd/system/.
$ mkdir /etc/systemd/system/devpi.service.d
$ cat <<EOF >/etc/systemd/system/devpi.service.d/custom.conf
[Service]
Environment=http_proxy=http://165.143.130.30:3128/
Environment=https_proxy=http://165.143.130.30:3128/
EOF

$ sudo systemctl daemon-reload
$ systemctl restart devpi.service

$ cat /etc/httpd/conf.d/devpi.conf
<VirtualHost 10.225.61.125:80>
    ServerName pip.telkom.co.za

    ServerAdmin webmaster@localhost
    DocumentRoot /var/www/devpi

    ErrorLog /var/log/httpd/devpi_error.log
    CustomLog /var/log/httpd/devpi_access.log combined

    #RequestHeader set X-outside-url "http://192.168.111.19"
    #RequestHeader set X-Real-IP "192.168.111.19"
    ProxyPass / "http://localhost:4040/"
    ProxyPassReverse / "http://localhost:4040/"
    <Directory /var/www/devpi>
        Options +Includes
    </Directory>
</VirtualHost>

$ systemctl reload httpd
```

Add the following entries to the `~/.pip/pip.conf` or `pip.conf` in your virtualenv on the client side.

```
[global]
index-url = https://devpi.server.co.za/root/pypi/+simple/
trusted-host = devpi.server.co.za

[search]
index = https://devpi.server.co.za/root/pypi/
trusted-host = devpi.server.co.za

[easy_install]
index_url = http://devpi.server.co.za/root/pypi/+simple/
```

From:

<https://wiki.dewberry.co.za/> - Shaun's Wiki

Permanent link:

<https://wiki.dewberry.co.za/doku.php?id=python&rev=1542882787>

Last update: **2019/09/16 16:09**

